

System Administrators,

- Do not apply the same fix twice. Always check the program to be sure that you need the change.
- Check the Creation-Date on your latest diskette. Based on that date, only apply the fixes that have been prepared since then.
- The Delta Symbol represents spaces when they are critical: **ΔΔΔ**.
- Zeroes have a dot in the center as follows: **000000**.

TECH NOTE # 1293, 10/08/08 **LOW-priority**.

DESCRIPTION: ERR 47 LINE 4430 CAZ735CV

TO CHECK: >LOAD "CAZ735CV"; LIST 4430

BEFORE:

```
04430 IF R8$(1,4)<>E$ THEN GOTO 04432 ELSE IF R8$(11,1)<>"A" THEN GOTO 04429
```

Do this fix if the line reads as above.

```
>EDIT 4430 C [ ] [IF (Z<57 OR Z>61) GOTO 4433 ELSE ]
```

```
>SAVE
```

AFTER:

```
04430 IF (Z<57 OR Z>61) THEN GOTO 04433 ELSE IF R8$(1,4)<>E$ THEN GOTO 04432
```

```
04430: ELSE IF R8$(11,1)<>"A" THEN GOTO 04429
```

TECH NOTE # 1294, 09/19/08 **LOW-priority**.

DESCRIPTION: NO-PROFILE message when restarting interrupts in Inquiry. See also 1290.

TO CHECK: >LOAD "CAS0360P"; LIST 3183

BEFORE:

```
03183 IF SW21$="21" THEN IF U0=21 THEN LET PZ1$=Z1$, Z1$(1,6)=Z1$(5,6)
```

Do this fix if the line reads as above.

```
>3183: ELSE IF U0=20 PZ1$=Z1$, Z1$(1,6)=Z1$(32,6)
```

```
>SAVE
```

AFTER:

```
003183 IF SW21$="21" THEN IF U0=21 THEN LET PZ1$=Z1$, Z1$(1,6)=Z1$(5,6) ELSE
```

```
03183: IF U0=20 THEN LET PZ1$=Z1$, Z1$(1,6)=Z1$(32,6)
```

TECH NOTE # 1295, 10/28/08 **LOW-priority.**

DESCRIPTION: ERR 38 LINE 2480 CAS1000P

TO CHECK: >LOAD "CAS0310P"; LIST 6064

BEFORE:

```
06064 IF DELK$<>"" THEN CALL "CAS1000P", Z2$, DELK$, "", "", "DEL"
```

Do this fix if the line reads as above.

```
>6064: ;DELK$=""
```

```
>SAVE
```

AFTER:

```
06064 IF DELK$<>"" THEN CALL "CAS1000P", Z2$, DELK$, "", "", "DEL"; LET DELK$=""
```